

Reference #: 13-004

Date: 29<sup>nd</sup> May, 2013

## AFP-2800 PCI v6.01.00

Dear Valued Customer,

Version 6.01.00 PCI is now released for the AFP-2800 and AFP-2802.

This upgrade includes the following changes;


- Added note to isolation wizard window to clarify that if you want to isolate multiple zones, it must have a space after the separation comma.
- Fixed an issue where PCI did not print zone options correctly. Now it shows AVF as well as alarm and latched options.
- Fixed an issue where if you printed a program and save .txt file 1st and followed by saving the pci file, it did not change the file extension back to "pci". As result it did not save any changes to the pci.
- Fixed an issue where a non firmware file could be selected and downloaded to the panel which causes the panel to irrecoverably fail.
- Fixed a bug where trying to open a configuration file that does not exist would create a fault message but then PCI would lose focus and could not be recovered.
- IntelliQuad sensitivity could be set to more than 6. This was wrong as the IntelliQuad can only have maximum of 6 sensitivity settings. PCI was changed to set sensitivity to default value of 3.
- Fixed an issue where the AAM wizard could program an input with a script if user selected and input address for the sounder. This would result in a F15 fault for the input module.

### Compatibility

- Compatible with all versions of AFP-2800 and AFP-2802 although it is recommended that all panels are upgraded to the latest firmware
- Compatible with Windows XP, Vista, 7 and 8

Contact your systems consultant for more information.

Sincerely,



James Edwards  
Product Manager